

Creating an app id-secret pair



Version: 1

Date Released: January 27, 2016

Document Number: AY006APP3-1



Introduction

This document provides information on creating a new app id-secret pair.

Audience

This document is written for OEM Admins.


Customer Support

Technical support is available through the Ayla Support website at:


<https://support.aylanetworks.com>, or via email at support@aylanetworks.com.

How to create a new app id-secret pair


In the OEM Dashboard, select **OEM Profile** from the main menu.




Select **Apps** in the menu at the top of the window.



Click **Create new application**.



The form opens.



Complete the form:


Name – name of the app

Application prefix – a prefix for the new app id and secret. This is a string.

Models The models you want to associate with the app, entered as a comma separated list.

Cloud to cloud – check if you want to use DSS (DataStream services)

Use sandbox for apns (changes need 10 minutes to take effect) – check if you want to connect to Apple's sandbox environment. Do not check if you want to use Apple's production service.



Click **Create**.

The new app-id is shown in the Apps list.

Oems > Ayla Networks Demo >			
Profile	Apps	iOS Certs	SMTP Settings
Email Templates	Social OAuth	Trigger Intervals	Host MCU Images
Application name	Application ID	Application Secret	Models
Ayla Smart Coffee Machine	aSmartCoffeeMachine-id	aSmartCoffeeMachine-twfrtNEe3ai9kQTLzqV3eg3...	COFE
Ayla Smart Thermostat	aSmartThermostat-id	aSmartThermostat-6196915	TEST
aylademo	aylademo-id	aylademo-4925875	
Light boxes	LBs-id	LBs-LzxcIRKJlmmUrdjG0jnoajmS...	LB1, LB2